



Movestick Mini driver installation guide from zip file


- 1) Unplug Movestick Mini from USB port.
- 2) Download Movestick_Mini_ant_usb2_drivers_ver1_2_40.zip driver packet
 - a. Material Bank
 - b. http://dm4.movescount.com/Movestick_Mini_ant_usb2_drivers_ver1_2_40.zip link
- 3) Select **Extract All...** by right click the download file on mouse.



- 4) You can give own destination folder or use default folder.



- 5) Click the Start button, then right click on My Computer and choose Properties. From the new window appearing, choose from the following:
 - a. Windows XP: Hardware – Device Manager
 - b. Windows Vista/7: Search on the left bottom corner “Device Manager”
 - c. Windows 8 and 8.1: Search on the top right corner “Device Manager”
- 6) Locate “libusb-win32 devices” on the list and click the small arrow beside it, which will reveal “ANT USB Stick 2” entry.



- 7) Right click “ANT USB Stick 2” and choose Properties – Driver – Update driver.
- 8) You will be asked if you would like to search the drivers online or browse for the driver in the computer. Choose the second option (browse from the computer) and choose the path where you extracted the driver files in step 4 and click Ok. The driver should update now and the watch should be recognized by the computer.
- 9) Driver installation should be completed successfully!